# Profitbase AS

# Profitbase Planner

# Configuration and Operation Sales by GM module

Profitbase

12.10.2020

Version 1.0



# Content


Cont	ent	2
1	Abstract, intended audience and pre-requisites	3
2	Common functionality	3
3	Principle of operation	5
	_Plan by year-totals or by month _Dimensionality _Additional input columns driven by sales	6
4	Module configuration	7
	_Publish and name moduleDefine dimensionalitySelect and name input columnsAttach module to input reportDefine input column to account mapping	7 8 9
5	Settings	.10
	_Distribution keys	

Date:	Version:	Changed by:	Changes:
29.5.2020	0.0	TN	Initial content
12.10.2020	1.0	TN	Revised

#### Abstract, intended audience and pre-requisites

The Profitbase Planner Configuration and Operation series consist of several documents dealing with the configuration and operation of individual Planner modules and functions.

Planner modules are operational input modules that contributors to the Budget and/or Forecast processes use to prepare the Profit & Loss (P&L) of their respective areas of responsibility. Different modules will typically cover parts of the P&L such as sales, personnel, cost, etc.



The modules are typically accessed from the Budget and Forecast summary workbooks and the input provided by the contributors are transformed into P&L transactions and fed back to the summary workbooks resulting in a P&L work-in-progress report summary.

The intended audience of this document is implementation partners configuring the solution initially and solution administrators responsible for operating it thereafter.

This document assumes that a Profitbase Planner solution has been deployed and that access to this solution is given to the reader.

The Sales by GM module is included as a standard Profitbase Planner module and is specific to the Budget process.

#### Common functionality

Changes made to input sheets are not saved automatically. To save changes, click the "Save" button. The "Save" button will remain disabled until a change has been made.

To undo all unsaved changes, click the "Refresh" button.

To undo the last of a series of unsaved changes, click the Ctrl and Z keys simultaneously.

To insert new rows to an input sheet, right-click in the sheet and select one of the available options:

- Insert row
- Insert row below



- Insert copy of row

To delete a row from an input sheet, right-click the row in question and select:

Delete row

Please note, that although the row is no longer visible in the input sheet, the change must be committed using the "Save" button or undone using the "Refresh" button.

In input sheets, editable fields are distinguished from non-editable fields by fill color, editable fields have by default a white fill color.

In setting tables, a so-called ranked input concept is often used for the dimensional context. Ranked input allows for a high-level selection of dimensional nodes and gives the opportunity to alter the rank or specificity between rows.

A ranked input cell can be set through the ranked input selector by clicking the cell value (cell will display 3 dots if no value is set):



The ranked input selector will display the dimensional hierarchy and allows for the selection of a high-level dimensional node. The selection of a high-level node implies that the setting applies to all sub-ordinate nodes.

Select node and click "OK".

Click "Cancel" to leave the selector without selecting.

In a table containing multiple rows, the rank or specificity of individual rows can be altered by moving the row up (decrease specificity) or down (increase specificity) by right-click the row in question and selecting:

- Move up
- Move down

The less specific the setting is, row should be high up in the table. The more specific the setting is, the further down in the table the row should reside.



#### 3 Principle of operation

The Sales by GM module provides an input sheet for the user to plan sales (amounts) per product and market and the associated gross margin % and other sales-related income and cost. Based on it, it generates sales and cogs related P&L transactions

# Plan by year-totals or by month

The Sales can be input as year-totals or as monthly values. This is controlled by the "Periods" button that toggles the input mode correspondingly:



Click the sicon to view the P&L transactions generated from the row in question.

A year-total input is automatically spread to the plan months of that particular year. The total is spread according to the monthly distribution function tied to the product and market as follows:

- If a specific monthly input has been made by the user, the distribution inherent in the monthly values is used as a distribution key.
- If not, then if a central distribution key is tied to the account, this distribution will be used

The existence of a central distribution key is indicated by the following symbol:



Click on the symbol to view the distribution key.

Please refer to <u>Distribution keys</u> for details on how to set up central distribution keys.

- If none of the above applies, the total is spread evenly over the plan months

If monthly values are input directly, the sum of the monthly values in a year are summed and the distribution used thereafter for year-total input will be the distribution inherent in those monthly values edited by the user.

The GM% is by default input as a year-total, but can be set specifically for individual months, by clicking the "Change" action link for the row in question. A popup will appear in which the GM% of individual months can be set:





To override, click the "Override" checkbox to open the monthly periods for editing.

To restore an already overridden row to its default ("Override" will be checked), uncheck the "Override" checkbox.

The Cost of Goods Sold is automatically calculated based on the sales and GM% inputs as:

Cost of Goods Sold = Sales \* ((100 – GM%)/100)

# Dimensionality

The basic dimensionality of the Sales by GM module is department, product, and market.

Extra dimensionality, limited to the Supplier dimension and the 4 free dimensions Dim1, Dim2, Dim3 or Dim4 may be added as needed. Please refer to <u>Define dimensionality</u> for details.

# Additional input columns driven by sales

In addition to sales and GM%, up to 5 additional input columns, may be added.


These additional columns will all be driven by the sales input and are therefore input as a percentage of the sales input. The resulting transactions will consequently inherit it's monthly distribution from the sales input.

Please refer to <u>Select and name input columns</u> for details.



#### Publish and name module


Select the "Input Settings and Administration" workbook and go to the "Setup" page:



Column	Description
Input module	The name of the input module
Dataset	The dataset or process that the module is attached to (Budget   Forecast)
Published	Indicates that the input module is Published or not (checked   unchecked)
ModuleExtensionID_Name	The module's default name
ModuleExtensionID_Name_EN	The module's English name
ModuleExtensionID_Name_NO	The module's Norwegian Name

# Define dimensionality

The dimensionality of a model is defined in the "Input settings and administration" workbook in the "Setup" page:




The Department, Product and Market dimensions are default and mandatory in any model.

Column	Description
DimensionColumn	The dimension column id. Preset.
Description	The measure's default description.
Description EN	The measure's English translation.
Description NO	The measure's Norwegian translation.
VisibleInput	Indicates whether dimension is visible (checked) or not (unchecked) in the input sheet of the model.
Mandatory	Indicates whether user must select a value from the dimension drop down when adding a row (checked) or not (unchecked) to the input sheet of the model.
Comment	Optional comment

# Select and name input columns

Select the "Input Settings and Administration" workbook and go to the "Setup" page:



There is a pre-set number of columns to select and name, Misc1 to Misc5.


Column	Description
Column Name	The internal column id
Column Name	The column default name
Column Name EN	The column's English translation
Column Name NO	The column's Norwegian translation
Input worksheet	Indicates that the column is visible and editable in the input worksheet or not (checked   unchecked)
Auto transaction	Indicates that the column is eligible for auto transactions or not (checked   unchecked). For details on auto transactions, see <a href="Auto transactions">Auto transactions</a> (optional)
Account mapping	Indicates that the column is eligible for account mapping or not (checked   unchecked). Note that any column which input is to be included in the Profit & Loss plan, need to be mapped to an account, see <a href="Define">Define</a> input column to account mapping



The module can be attached to the action link button of one or more report lines of the Forecast summary report:



To attach the module to a report line, go to the "Setup" page of the "Input settings and administration" workbook:



Column	Description
Departm.	Source department. Ranked input. Mandatory.
	Through the use ranked input (high level selection), different modules may attach to a given report line for different part of the department dimension (organization).
Report Line ID	Report line to which input module is to attach. Select from list. Mandatory.
Input module	Input module to attach. Select from list. Mandatory.


## Define input column to account mapping

The Sales and calculated Cost of Goods Sold must be mapped to accounts for the P&L transactions to be generated.

The same applies to any additional input columns defined and that should generate P&L transactions.

The input column to account mapping is found in the "Input settings and administration" workbook in the "Budget settings" page:





Column	Description
Department	Source department. Ranked input. Mandatory.
Product	Source product. Ranked input. Mandatory.
Market	Source market. Ranked input. Mandatory.
Column Name	Input column for which the account mapping applies. The drop-down list will by default contain Sales and Cogs. If additional input columns are defined and they should produce P&L transactions, they will have to be set up with an "Account mapping", check mark in the input column setup. Please refer to Select and name input columns for details.
Account	The target account, i.e. that account that the generated P&L transaction will be tied to.
Comment	Optional comment

#### 5 Settings

The settings for the Sales by GM module are found in the "Input settings and administration" workbook in the "Budget settings" page.

## Distribution keys

Distribution keys are specified by the combination of the department, product, and market dimensions.

The dimensional values are selected using the ranked input selector. For details on using the ranked input selector and making rank changes between rows, please refer to <a href="Common functionality">Common functionality</a> for details.

As a general rule-of-thumb, it is advisable not to use too specific distribution keys.



Column	Description
Department	Ranked input. Mandatory
Product	Ranked input. Mandatory.
Market	Ranked input. Mandatory.




ColumnName	The column name for which the distribution key applies, see
Monthly distribution key	Numeric values. Mandatory.
weight (heading dynamic)	When distributing a year-total value over monthly periods, the weight given to a specific month is its distribution key weight divided by the sum of the distribution key weights for all the months for that year.
Comments	Optional comment. Note that if a comment is added, the contributor will see the comment when viewing the distribution key of an input row.

# Auto transactions (optional)

Auto-transactions may be used to trigger additional transactions based on user input. For example, the input to a certain account should always generate an additional transaction to another account amounting to 10% of the input or source transaction.

The target department will always be the same as the input or source department.



Column	Description
Department	Source department. Ranked input. Mandatory
Product	Source product. Ranked input. Mandatory.
Market	Source market. Ranked input. Mandatory.
Value	The value and the operator define how the amount of the target transaction will be calculated. In the example above, the amount of the target transaction will be 10% o
	Numeric value. Mandatory.
Operator	Select from list. Mandatory.
Condition	Optional. Special condition to apply when validating whether to execute the rule or not.
	For example:  - Month() > 6 indicating that rule will be executed only for transactions with a transaction date with month number greater than 6 (June)  - CurrentPeriodValue() > 1000 indicating that rule will be executed if value currently processed is greater than 1000
	Operators: - Equality: == - Greater than or equal to: >= - Less than or equal to: <= - Logical and: && Logical or:
Target Account	The account that the target transaction will have.

